


## Connecting to eduroam on a Chromebook laptop


You will first need to configure your laptop in order to connect to eduroam. To do this you will need to download and install a configuration tool. This can be done by connecting to the StrathWifiSetup network available in the Library and Student Residences. The following instructions show the steps for doing so on a Chromebook laptop. Different versions of Chrome OS may vary slightly in layout but the process will remain the same. You will only need to configure your device once and thereafter it will automatically connect to eduroam.



1. Click on the Wi-Fi icon.

2. In the pop-up menu, click on the Network button.


3. Click on StrathWifiSetup.




4. Open a browser, and go to [cat.eduroam.org](http://cat.eduroam.org). Scroll down.



5. Click on Click here to download your eduroam installer.



6. In the pop-up window that appears, enter Strathclyde.



7. Click on University of Strathclyde.



University of  
**Strathclyde**  
**Glasgow**



Configuration Assistant Tool

Start page

## University of Strathclyde

If you encounter problems, then you can obtain direct assistance from your organisation at:

WWW: <https://www.strath.ac.uk/professionalservices/it/wifi/>


email: [helpdesk@strath.ac.uk](mailto:helpdesk@strath.ac.uk)

tel: 0141 548 4444

This entry was last updated at: 2022-08-25 16:00:28



Download your installer for Chrome OS



[Choose another installer to download.](#)

8. Click on eduroam.

eduroam®

After downloading the file, open the Chrome browser and browse to this URL: <chrome://network>. Then, use the 'Import ONC file' button. The import is silent; the new network definitions will be added to the preferred networks.

Continue

9. In the drop-down menu, click on Continue.

## Mobile activation

Open Mobile Activation UI

## Reset eSIM profile cache

Reset eSIM profile cache

## Disable eSIM profiles

Disable active eSIM profile

## Reset eSIM

Reset eSIM

## Reset ApnMigrator


Reset ApnMigrator

## New Wi-Fi Network Dialogue

Show 'Add new Wi-Fi' dialogue


## Import ONC file

Choose File No file chosen



10. Once the download is complete, open a browser, and go to `chrome://network/#general`. Scroll down.


11. Under Import ONC file, click on Choose File.




12. In the pop-up window that appears, select eduroam-chromeos-UoS-Eduroam\_..., then click on Open.

13. Click on the Wifi icon.


14. In the pop-up menu, click on the Network button.




15. Click on StrathWifiSetup.



16. In the Network Settings window, click on Forget.



17. Click on Wifi.



18. Click on eduroam.

**Join Wi-Fi network**

SSID  
eduroam

Security  
EAP

EAP method  
PEAP

EAP Phase 2 authentication  
MSCHAPv2

Server CA certificate  
University Of Strathclyde Network Support Root CA 1 [University ▾]

Subject match

Subject alternative name match  
DNS:eduroam.strath.ac.uk

Domain suffix match

Cancel Connect

University Of Strathclyde Network Support Root CA 1 [University ▾]

Subject match

Subject alternative name match  
DNS:eduroam.strath.ac.uk

Domain suffix match

Identity

Password

Anonymous Identity  
anonymous@strath.ac.uk

Save identity and password

Cancel Connect

19. In the pop-up window that appears, scroll down.

20. Where it says Identity, enter your username followed by @strath.ac.uk. For example, pkb09111@strath.ac.uk.

Where it says Password, enter your password.

Click on Connect.

Was this information helpful?

## CONTACT US

**Email:** [help@strath.ac.uk](mailto:help@strath.ac.uk) **Call:** 0141 548 4444